



Usage instructions:

1. Launch the product via 1-click. **Please wait until** the instance passes all status checks and is running. You can connect using your Amazon private key and 'ubuntu' login via your SSH client.

To update software, use: **sudo apt-get update -y**

2. Next, change in the authentic directory, use:

cd ~/.docker/compose/authentik

3. Start the Docker Container:

docker compose up -d


```
ubuntu@ip-172-31-29-207:~$ cd ~/.docker/compose/authentik
ubuntu@ip-172-31-29-207:~/.docker/compose/authentik$ docker compose up -d
[+] Running 5/5
  ✔ Network authentik_default          Created
  ✔ Container authentik-redis-1        Started
  ✔ Container authentik-postgresql-1   Started
  ✔ Container authentik-worker-1       Started
  ✔ Container authentik-server-1       Started
ubuntu@ip-172-31-29-207:~/.docker/compose/authentik$
```

4. Once the images have started, in a web browser log into the Authentik interface for initial startup.

http://<your Instance Public IP>:9000/if/flow/initial-setup/

For ex: http://36.365.23.3:9000/if/flow/initial-setup/

Note: Complete the registration. If you have difficulty, refresh your web page.



authentik

Applications



No Applications available.

Either no applications are defined, or you don't have access to any.

Create a new application

Refer to documentation



0



Admin interface

akadmin



Search...



authentik



Welcome, authentik Default Admin.

General system status

User interface

Dashboards

Overview

User Statistics

System Tasks

Applications

Events

Customization

Flows and Stages

Directory


System

Enterprise


Quick actions

- Create a new application
- Check the logs
- Explore integrations
- Manage users
- Check the release notes

Outpost status



Sync status



Recent events

Action	User	Creation ...	Client IP
Model updated authentik.events.middle ware	akadmin	55 seconds ago 7/25/2024, 1:58:12 P M	68.14.104.156 Newington, US, I A
Login authentik.events.signals	akadmin	1 minute ago 7/25/2024, 1:57:51 P M	68.14.104.156 Newington, US, I A
User was written to authentik.events.signals	akadmin	1 minute ago 7/25/2024, 1:57:51 P M	68.14.104.156 Newington, US, I A
Model updated authentik.events.middle ware	Anonymous us er	1 minute ago 7/25/2024, 1:57:51 P M	68.14.104.156 Newington, US, I A
Password set authentik.events.signals	akadmin	1 minute ago 7/25/2024, 1:57:50 P M	255.255.255.2 5

System status



OK
Everything is ok.

Version



2024.6.1
Up-to-date!

Workers



1

For more configurations, see documentation:

<https://docs.goauthentik.io/docs/installation/configuration#about-authentik-configurations>

AWS Data

- Data Encryption Configuration: This solution does not encrypt data within the running instance.
- User Credentials are stored: /root/.ssh/authorized_keys & /home/ubuntu/.ssh/authorized_keys
- Monitor the health:
 - Navigate to your Amazon EC2 console and verify that you're in the correct region.
 - Choose Instance and select your launched instance.
 - Select the server to display your metadata page and choose the Status checks tab at the bottom of the page to review if your status checks passed or failed.

Extra Information: (Optional)

Allocate Elastic IP

To ensure that your instance **keeps its IP during restarts** that might happen, configure an Elastic IP. From the EC2 console:

1. Select ELASTIC IPs.
2. Click on the ALLOCATE ELASTIC IP ADDRESS.
3. Select the default (Amazon pool of IPv4 addresses) and click on ALLOCATE.
4. From the ACTIONS pull down, select ASSOCIATE ELASTIC IP ADDRESS.
5. In the box that comes up, note down the Elastic IP Address, which will be needed when you configure your DNS.
6. In the search box under INSTANCE, click and find your INSTANCE ID and then click ASSOCIATE.
7. Your instance now has an elastic IP associated with it.
8. For additional help: <https://docs.aws.amazon.com/AWSEC2/latest/UserGuide/elastic-ip-addresses-eip.html>